



**Deltek + PROPRICER**

# ProPricer Installation Guide

# Contents

About ProPricer .....	1
Minimum Requirements .....	2
ProPricer Client .....	2
Physical Machine or Virtual Desktop Infrastructure .....	2
Virtual Application Only .....	2
ProPricer Application Server .....	3
Database Server .....	3
On-Premises .....	3
Cloud .....	3
SQL Database Initial Starting Sizes .....	3
Windows Operating System Compatibility .....	4
ProPricer Architecture .....	5
Client-Server Communication .....	5
WebSocket Duplex Channel .....	5
Security .....	6
ProPricer Data Model (API) .....	6
Data Model Terms .....	6
Data Model .....	6
User Interface .....	7
Reports .....	7
Databases .....	8
Advantages .....	8
Disadvantages .....	8
Things to Consider Before Installation .....	9
ProPricer Database Components .....	9
How a ProPricer Database Works .....	9

---

ProPricer Connectivity .....	10
Downloading ProPricer .....	11
ProPricer Installation File Types .....	11
Installing ProPricer Application Server .....	12
Upgrading the Application Server .....	13
SSL Certificate .....	14
ProPricer ServerConfig .....	14
Using ServerConfig to configure your ProPricer endpoint .....	15
Advanced server configuration .....	16
Schema notes .....	17
Certificate sources .....	18
SSL certificate requirements .....	18
Self-signed certificates .....	19
Using a self-signed certificate .....	20
Azure Active Directory (AD) Setup .....	24
Creating an application registration .....	24
Using ServerConfig to configure your Azure AD logins for ProPricer .....	25
ProPricer Database Setup .....	26
SQL Server Database Required Information .....	26
Oracle Database Required Information .....	27
SQL Server Database Setup .....	27
Oracle Database Server Setup .....	29
ProPricer Application Server Oracle Setup .....	30
Creating a Database Upgrade Script .....	31
Upgrading the Database .....	32

---

Windows Service Account Configuration .....	33
ProPricer Server Manager .....	34
Using ProPricer Server Manager .....	34
Ask Dela Setup .....	35
Creating an Azure AI service .....	35
Creating required models .....	36
Setting up ProPricer Server .....	36
ProPricer Client .....	37
Installing the ProPricer Client .....	37
Upgrading the ProPricer Client .....	39
All-In-One Installation .....	40
Troubleshooting a Connection Error .....	40
Remote Desktop Services or Citrix Server .....	43
Prerequisites .....	43
Downloads .....	43
Installing the ProPricer Client on a Remote Desktop Services or Citrix Server .....	43
Command Line Arguments for ProPricer Tools .....	44
Database Setup: ProPricerDatabaseSetup.exe .....	44
Usage for MSSQL .....	44
Usage for Oracle .....	44
Options .....	45
ProPricer ServerConfig: ProPricerServerConfig.exe .....	47
Usage .....	47
Options .....	47
Server Manager: ProPricerServerManager.exe .....	47
Usage .....	47
Options .....	47

Silent Installation, Upgrade, or Removal .....	48
Running a Silent Installation .....	48
Recording the Installation Process .....	48
Running a Silent Upgrade .....	49
Running a Silent Removal .....	49
Contact Us .....	50

---

# About ProPricer

The ProPricer™ Installation Guide is a system administrator's reference for setting up and maintaining ProPricer and its supporting databases.

The current version of ProPricer operates in a three-tier architecture that includes an application client, an application server, and a database.

The application client is a “thick” client, meaning most of the processing work is done on the client.

The application server is a service that uses special serialization to minimize the size of transferred data, so clients are quickly and easily synchronized with the database. The service is managed by a program called ProPricer Server Manager. Additionally, the ProPricer client can connect to multiple databases through a single application server.

ProPricer supports both Microsoft SQL Server and Oracle databases. Each database type can be created with the ProPricer Database Setup program. Both SQL Server and Oracle databases have unique characteristics and uses in the workplace. The functionality and display of ProPricer are the same, regardless of the database type.

---

# Minimum Requirements

## ProPricer Client

### Physical Machine or Virtual Desktop Infrastructure

- RAM
  - Minimum: 4 GB
  - Recommended: 8 GB
- Processor
  - 64-bit
  - Minimum speed: 1.4 GHz
  - Recommended speed: 2.0 GHz or faster
- Hard drive space: 500 MB (excluding database)
- .NET 8 (not included with installation)

### Virtual Application Only

- RAM
  - Minimum: 1 GB
  - Recommended: 2 GB
- Processor
  - 64-bit
  - Minimum speed: 1.4 GHz
  - Recommended speed: 2.0 GHz or faster
- Hard drive space: 10 MB (for user profiles only)
- .NET 8 (not included with installation)

## ProPricer Application Server

- RAM
  - 1-50 users: 4 GB
  - Every 50 additional users: Increase by 2 GB
- Processor
  - 64-bit
  - Minimum: 1.4 GHz
  - Recommended: 2.0 GHz or faster
- Hard drive space: 500 MB (excluding database)
- .NET 8 (not included with installation)

## Database Server

### On-Premises

- Microsoft SQL Server 2014 SP3 or newer (Recommended: SQL Server 2016 SP3 or newer)
- Oracle 12c or newer (Recommended: Oracle 19c or newer)

### Cloud

- Azure SQL (Azure SQL Database or Azure SQL Managed Instance)
- Amazon RDS (SQL Server or Oracle)

## SQL Database Initial Starting Sizes

- Without tutorial
  - Data: 6.25 MB
  - Log: 12 MB
- With tutorial
  - Data: 9.25 MB
  - Log: 14.60 MB



## Windows Operating System Compatibility

- Windows 10
- Windows 11
- Windows Server 2016
- Windows Server 2019
- Windows Server 2022


# ProPricer Architecture

This section of the installation guide explains the structure of the ProPricer client, server, database, and their administrative programs.

## Client-Server Communication

The communication between ProPricer clients and the server is implemented with WebSockets in ASP.NET Core using Microsoft .NET 8. ProPricer 9 Application Server implements Kestrel web server, so it does not need a separate web server (for example, Internet Information Services for Windows Server).

WebSocket is a protocol that enables two-way persistent communication channels over TCP connections. It supports a non-blocking, asynchronous operation between clients and services where a sequence of operations is executed out of time coincidence with any event. The asynchronous method uses message queues as the transport for delivery and receipt of the message of threads. WebSocket also supports operations that occur without a regular or predictable time relationship to a specified event.



## WebSocket Duplex Channel

A “duplex” message exchange pattern is based on a series of one-way interactions that form a complete conversation. For example, a long running operation can be started by a single method call for which the client does not have to wait for completion. The server can then periodically notify the caller about the percentage of work that has been completed.

## Security

SSL protocols are for encrypting and decrypting traffic between the client and server. ProPricer Application Server (Kestrel) uses the system default TLS protocol versions. This allows TLS 1.3 to be used by default in environments that support it, but it also allows TLS 1.0 to be used in some environments (such as Windows Server 2016 by default). You can configure specific TLS versions to be used, or you can block them.


## ProPricer Data Model (API)

The ProPricer data model can be made accessible to other applications with our Application Programming Interface (API). Our API provides access to all the data in a ProPricer database.

### Data Model Terms

- BOM: Business Object Model
- DAL: Data Access Layer
- BO: Business Object
- DTO: Data Transfer Object
- DBO: Data Buffer Object
- DPO: Data Persistent Object

### Data Model




## User Interface

- Standard components of the ProPricer user interface such as tabs, forms, textboxes, labels, buttons, and grids come from the third party developer, DevExpress WinForms.
- In multi-user environments, ProPricer data is updated automatically without the need to manually refresh.
- The user interface allows multiple tabs to be open but does not support running multiple processes at the same time.

## Reports

ProPricer 9 uses the following report engine model for its Report Designer feature.



---

# Databases

The enterprise versions of Microsoft SQL Server and Oracle databases are primarily used by larger companies that have more data to store in ProPricer, require better security, or need better reliability. The express versions of these databases are used by smaller companies that might only have a few users.

- If your company uses more than one database, all of them can be handled by the same application server.
- The minimum requirements are listed the [Database Server](#) section of this guide.

Following are the advantages and disadvantages of using SQL Server or Oracle databases, as well as some other things to consider before installation.

## Advantages

- The databases are robust. Data corruptions hardly ever occur.
- An unlimited number of users can reliably connect to the databases.
- There is no limit on storage capacity, except when express versions are used.
- The databases are secure. An end user cannot access them without the proper permissions.
- The databases are usually located on their own server. This reduces the impact of network traffic.
- The databases are easy to back up.

## Disadvantages

- There must be IT infrastructure in place to support SQL Server and Oracle databases. Maintenance of the databases must be done by a database administrator, which could be an added cost.
- These databases are more expensive, although there are free express versions of both SQL Server and Oracle. For full enterprise versions, a powerful server must house the databases so it can handle all the ProPricer functions and users connecting to them.
- The databases are potentially difficult to restore. The restore process can take anywhere from a few hours to all day. This depends on the size of the databases.

---

## Things to Consider Before Installation

### ProPricer Database Components


- System data: Information about ProPricer users, rights, settings, etc.
- Global data: Libraries and rate tables shared between proposals.
- Proposal-specific data: Information entered or used in a certain proposal.

### How a ProPricer Database Works

- The entire ProPricer database, including system, global, and proposal data is stored in a single Oracle or SQL Server database.
- The ProPricer database does not require a dedicated Oracle or SQL Server database. Any Oracle or SQL Server database can be used without affecting the existing applications and data. However, ProPricer does require that its data be separated from all other data in the database. It also requires full privileges to modify its own data, including future database upgrades.
- There is no relationship between ProPricer users and database users. ProPricer users are part of their own security model, which is used to restrict access to certain ProPricer areas. ProPricer does not rely on or use any SQL Server or Oracle security capabilities.
- Only the application server communicates with the database, and it only uses one SQL Server or Oracle user account to do it. The application server then sends data to the ProPricer clients, which can have many user accounts. Additionally, a single application server can support multiple databases.
- It is highly recommended that the application server and the database are located in the same data center or Azure virtual network. Issues may arise if the application server attempts to connect to databases in multiple locations.
- To use ProPricer with an Oracle database, the server and client must be installed and configured as described in the [Oracle Database Server Setup](#) and [Oracle Client Setup](#) sections of this guide.
- Connection information is placed in an encrypted format in a central location. End users only see descriptive information about existing ProPricer databases. ProPricer extracts and uses connection information via the application server, which is only accessible to system administrators.
- When working with an SQL Server or Oracle database, ProPricer uses a "thin" server, which creates database constraints to ensure data integrity. Logical rules are enforced and applied by the ProPricer client.
- Currently, no SQL Server or Oracle multi-user capability is needed, because ProPricer uses its own locking schema via the application server to resolve multi-user conflicts. This is based on ProPricer logical units, not database tables or records.

## ProPricer Connectivity

Linking multiple ProPricer applications to the same application server allows users to easily share data. A single ProPricer application can be used to input all data, which eliminates duplicate data entry issues and allows for some configuration control.



- If your company uses more than one database, all of them can be handled by the same application server.

To learn more about the ProPricer architecture, see the [ProPricer Architecture](#) section of this guide.

All editions of ProPricer, such as Contractor Edition and Government Edition, can connect to the same application server and database.

---

# Downloading ProPricer

Go to the ProPricer Support Portal at [downloads.propricer.com](https://downloads.propricer.com) to download the installation files.

- The ProPricer client and application server installed must be the same version number.

If a [silent installation](#) with Microsoft System Center Configuration Manager (SCCM) is preferred, the correct .zip file needs to be downloaded and extracted to a folder. For example, the file for Contractor Edition is called 9\_5\_104\_0\_pp\_ce\_client\_sccm.zip, and the file for subscription licenses is 9\_5\_104\_0\_pps\_ce\_client\_sccm.zip. The Windows File Explorer can be used to extract these files.

## ProPricer Installation File Types

- Application server: Designed to install ProPricer Application Server, ProPricer Server Manager, and ProPricer Database Setup.
- Client application: Designed to install the ProPricer client, ProPricer Client ConfigTool, and ProPricer Custom Data Manager.
- Client, server, and MSSQL Express (all-in-one): Designed for standalone installations. This puts the ProPricer client, application server, and an MSSQL Express database on the same system and connects them.



---


# Installing ProPricer Application Server

1. Double-click the ProPricer Application Server installation file.
2. Read the details about the installation process. When you are ready to begin, click Next.
3. Accept the default location for the installation, or click Browse to select a different folder, then click Next.
4. If needed, change the program folder's name, then click Next.
5. Review the installation settings, then click Install.
6. Select Launch ProPricer Database Setup, then click Finish.
7. Follow the instructions in [ProPricer Database Setup](#) to create or upgrade existing databases.

# Upgrading the Application Server

To upgrade, the latest ProPricer Application Server installation file is required.

1. Double-click the ProPricer Application Server installation file.
2. Read the details about the upgrade process. When you are ready to begin, click Next.
3. A message will warn you that your data will be temporarily inaccessible while upgrading. Click Yes to continue the upgrade process.



4. Click Finish.

# SSL Certificate

ProPricer Application Server requires an SSL certificate to encrypt the communication between client and server. Before installation, ensure that you have an SSL certificate that meets all the [requirements](#), and you have the password for it, if needed.

Advanced users can manually configure multiple endpoints, including the URLs and the certificates to use, either from a file on disk or from a certificate store. For a single endpoint, manual configuration is not required or recommended. Instead, use ProPricer ServerConfig.

## ProPricer ServerConfig

ProPricer ServerConfig is designed to validate your SSL certificate and configure a single endpoint.

Before using the tool, verify that the certificate meets the [requirements](#) and is installed in the Local Machine location.

With ProPricer ServerConfig, no manual configuration is needed. As long as your certificate is valid, the tool creates or edits the following files for you:

- `ProPricerServer.config.json`
- `ProPricerServerManager.config.json`

When you use an invalid certificate (for example, a self-signed certificate), the tool creates or updates `ProPricerServerManager.config.json` and `EBS.ProPricer.Client.config.json` with the certificate serial number. It also updates the host and port in `ProPricerServerManager.config.json`, and the endpoint information in `ProPricerServer.config.json`.

If ProPricer ServerConfig finds any syntax errors in your configuration files, it explains what they are and where to find them. The tool can then automatically fix the errors when it updates the files.

## Using ServerConfig to configure your ProPricer endpoint

1. Verify that your SSL certificate meets the [requirements](#).
2. Install your certificate in the Local Machine location.
3. Run `propricerserverconfig.exe` to start ProPricer ServerConfig.
4. Next to the Certificate Name field, click the Load from store button.
5. When selecting a store, Local Machine is the only Location option. In the Name field, select the store that has the certificate.
6. Click Search.
7. Select the certificate that was found, or click More Choices to select a different certificate in the store, then click OK.
8. The Host field will have valid names from the certificate's subject. If needed, you can edit the Host and Port values.
  - If you use a wildcard certificate, edit the Host value so it is a valid host name (fully qualified domain name).
9. The Keep Alive Interval (sec) field determines how often a signal is sent to the server to maintain a connection. Enter the length of time as a number of seconds. The default is 15 seconds.
10. The Remote Inactivity Timeout (sec) field determines how long inactivity can last before a connection closes. Enter the length of time as a number of seconds. The default is 30 seconds.
  - ProPricer utilizes a duplex channel, so both the client and server send messages and should have the same, or at least compatible, settings. Both parties periodically send KeepAlive messages to notify the other party they are still alive. If no message is received from the other party during the Remote Inactivity Timeout, then the party (client or server) closes the underlying connection.
  - Remote Inactivity Timeout should be equal to or greater than double the Keep Alive Interval.
11. Click Apply.
12. If your certificate is invalid, a warning will appear. Click Yes to continue and complete the configuration. The tool will create or edit `ProPricerServer.config.json`, `ProPricerServerManager.config.json`, and `EBS.ProPricer.Client.config.json`

## Advanced server configuration

If ProPricer ServerConfig does not meet your needs, you can edit the configuration files on your own.

This example shows the configuration of an HTTPS endpoint for `propricerserver.mycompany.com` using port 8092, and a certificate stored in the Local Machine location:

```
{
  "Kestrel": {
    "Endpoints": {
      "Https": {
        "Url": "https://propricerserver.mycompany.com:8092",
        "Certificate": {
          "Subject": "propricerserver.mycompany.com",
          "Store": "My",
          "Location": "LocalMachine",
          "AllowInvalid": "false"
        }
      }
    }
  }
}
```

## Schema notes

Set `AllowInvalid` to `true` to permit the use of invalid certificates (for example, self-signed certificates).

Any HTTPS endpoint that doesn't specify a certificate (`HttpsDefaultCert` in the preceding configuration example) falls back to the certificate defined under `Certificates:Default` or the development certificate.

Endpoint names are case-insensitive. For example, `HTTPS` and `Https` are equivalent.

The `Url` parameter is required for each endpoint, and it must begin with `https`. An endpoint will be unreachable if you enter `http` instead. The format for this parameter is the same as the top-level `Urls` configuration parameter, except that it is limited to a single value.

These endpoints replace those defined in the top-level `Urls` configuration rather than adding to them. Endpoints defined in code via `Listen` are cumulative with the endpoints defined in the configuration.

The `Certificate` section is optional.

- If the `Certificate` section isn't specified, the defaults defined in `Certificates:Default` are used.
- If no defaults are available, ProPricer Server loads all valid certificates by default.
- If there are no defaults and no certificate is present, the server throws an exception and fails to start.

The `Certificate` section supports multiple certificate sources.

Any number of endpoints may be defined in the configuration, as long as they do not cause port conflicts.

## Certificate sources

Certificate nodes can be configured to load certificates from a number of sources:

- `Path` and `Password` to load `.pfx` files.
- `Path`, `KeyPath`, and `Password` to load `.pem/.crt` and `.key` files.
- `Subject` and `Store` to load from the certificate store.

For example, the `Certificates:Default` certificate can be specified as:

```
"Default": {  
  "Subject": "<subject; required>",  
  "Store": "<cert store; required>",  
  "Location": "<location; defaults to CurrentUser>",  
  "AllowInvalid": "<true or false; defaults to false>"  
}
```

Reference: <https://learn.microsoft.com/en-us/aspnet/core/fundamentals/servers/kestrel/endpoints?view=aspnetcore-6.0#replace-the-default-certificate-from-configuration-1>

## SSL certificate requirements

A valid SSL certificate is required. ProPricer Application Server will not start if there are no valid SSL certificates installed or configured.

The SSL certificate must comply with the following requirements:

- It is intended for server authentication and client authentication.
  - The key pair must be generated properly because a private key is required.
  - Enhanced Key Usage must contain Server Authentication (1.3.6.1.5.5.7.3.1).
- It has Subject Alternative Name (OID value: 2.5.29.17).
- It is valid (not expired, and trusted by server and client machines).
  - To permit the use of invalid certificates (for example, self-signed certificates) set `AllowInvalid` to `true`.

---

## Self-signed certificates

You can use self-signed certificates with ProPricer. The all-in-one installer generates a self-signed certificate using the computer name, and the configuration allows this certificate to be used across the ProPricer application server, client, and tools like Server Manager.

If you want to use a self-signed certificate, the certificate must comply with the certificate requirements, and you must allow the usage of it. By default, self-signed certificates are not allowed.

After configuring the SSL certificate on the server using ProPricer ServerConfig, copy `EBS.ProPricer.Client.config.json` to all clients. This allows using the invalid certificate.



## Using a self-signed certificate

1. Create the self-signed certificate for server authentication.
  - You can generate the certificate using OpenSSL or other tools, and add it to the Local Machine location.
  - Use your desired domain as your endpoint. You can use `localhost` to only accept connections from your local computer. You can use the computer name to accept connections from the LAN. You can use a fully qualified domain name to accept connections from the internet.
2. ProPricer Application Server will load all certificates available automatically. Alternatively, you can specify which certificate to use for each endpoint:

```
{
  "Kestrel": {
    "Endpoints": {
      "Https": {
        "Url": "https://propricerserver.mycompany.com:8092",
        "Certificate": {
          "Subject": "propricerserver.mycompany.com",
          "Store": "My",
          "Location": "LocalMachine",
          "AllowInvalid": "true"
        }
      }
    }
  }
}
```

### 3. Allow invalid certificates on Client Config:

- Edit the file `EBS.ProPricer.Client.config.json`.

- Go to the `CertificateValidation` section:

```
"CertificateValidation": {  
  // "AllowAny": "True"  
  // "AllowedIds": [ "43aece0568e2f8e4b761f20da78ddcf"  
}
```

- To only permit the invalid certificate, enter its serial number in `AllowedIds`:

```
"CertificateValidation": {  
  // "AllowAny": "True"  
  "AllowedIds": [ "46C220213F4713B0419DF68140FF9BC8"  
}
```

- Alternatively, you can remove the comment `AllowAny: "True"` to allow all invalid certificates to be used by Client Config. This is recommended when the client connects to multiple servers:

```
"CertificateValidation": {  
  "AllowAny": "True"  
  // "AllowedIds": [ "46C220213F4713B0419DF68140FF9BC8"  
}
```

#### 4. Allow invalid certificates on ProPricer Server Manager:

- Edit the file `ProPricerServerManager.config.json`.
- Go to the `CertificateValidation` section:

```
"CertificateValidation": {  
  "AllowAny": false,  
  "AllowedIds": [ ]  
}
```

- To permit the invalid certificate, enter its serial number on `AllowedIds`:

```
"CertificateValidation": {  
  "AllowAny": false,  
  "AllowedIds": ["46C220213F4713B0419DF68140FF9BC8"]  
}
```

- Alternatively, you can change `AllowAny` to `true` to allow all invalid certificates to be used by Server Manager:

```
"CertificateValidation": {  
  "AllowAny": true  
  // "AllowedIds": ["46C220213F4713B0419DF68140FF9BC8"]  
}
```

## 5. Allow invalid certificates on the ProPricer client:

- Edit the file `EBS.ProPricer.Client.config.json`.

- Go to the `CertificateValidation` section:

```
"CertificateValidation": {  
  // "AllowAny": "True"  
  // "AllowedIds": [ "43aece0568e2f8e4b761f20da78ddcf"  
}
```

- To only permit the invalid certificate, enter its serial number in `AllowedIds`:

```
"CertificateValidation": {  
  // "AllowAny": "True"  
  "AllowedIds": [ "46C220213F4713B0419DF68140FF9BC8"  
}
```

- Alternatively, you can remove the comment `AllowAny: "True"` to allow all invalid certificates to be used by the ProPricer client. This is recommended when the client connects to multiple servers:

```
"CertificateValidation": {  
  "AllowAny": "True"  
  // "AllowedIds": [ "46C220213F4713B0419DF68140FF9BC8"  
}
```

# Azure Active Directory (AD) Setup

ProPricer supports Azure AD logins. To enable Azure AD logins, follow the procedure for creating an application registration, and use ProPricer ServerConfig to point to it.

The following procedures in this section are optional. However, completing the steps will allow users to authenticate with your Azure AD tenant, and your authentication methods, such as multi-factor authentication, will be enforced.

## Creating an application registration

1. Sign into the Azure Portal.
2. If you have access to multiple tenants, use the Directory + subscription filter in the top menu to switch to the tenant in which you want to register the application.
3. Search for and select Azure Active Directory.
4. Under Manage, select App registrations > New registration.
5. Enter a display name for your application. For example, ProPricer 9.
6. Specify who can use the application, sometimes called its sign-in audience. Accounts in this organizational directory only is recommended.
7. Under Redirect URI (Optional), leave the fields blank.
8. Click Register. Wait for the application registration creation.
9. Under Manage, select Authentication > Add a platform.
10. Go to Configure platforms and select Mobile and desktop applications.
11. Select all redirect URI checkboxes, then click Configure.
12. Click Save.
13. Go to API registration and select Grant admin consent for your tenant.
14. Under Overview, copy the Application (client) ID and Directory (tenant) ID. You will need this information in [Step 3 of the next procedure](#).

Reference: <https://docs.microsoft.com/en-us/azure/active-directory/develop/quickstart-register-app>

---

## Using ServerConfig to configure your Azure AD logins for ProPricer

1. Complete your [endpoint configuration](#).
2. Under Azure AD, select an Instance option. Typically, ProPricer customers select Azure US Government.
3. In Tenant ID and Client ID, paste the Directory (tenant) ID and Application (client) ID copied during [step 14 of the previous procedure](#).
4. Click Apply.
5. Restart the application server service to apply the changes.
  - When your setup is complete, open the ProPricer client to create users with Azure AD logins. Ensure that your System Options allow this login type.

---

# ProPricer Database Setup

Use the ProPricer Database Setup program to create a new SQL Server or Oracle database, upgrade an existing database, or create the ProPricer data structure within an existing SQL Server or Oracle database.

- If your company uses more than one database, all of them can be handled by the same application server.

Currently there is no special utility tool for converting an SQL Server database to an Oracle database or vice versa. Instead, use the ProPricer Archive/Restore features to move data between SQL and Oracle databases.

## SQL Server Database Required Information

The following information is required:

- Database Name
- Database Server Name
- Login ID and Password for SQL Server authentication

The following information is not required, but you can provide it if needed:

- Database Data File: Path and Filename, Size, Max Size, and File Growth
- Database Log File: Path and Filename, Size, Max Size, and File Growth

## Oracle Database Required Information

- Host Name: The IP address or name of the host for the Oracle server.
- Port Number: The Oracle TCP/IP port. The default is 1521.
- Service Name: The Oracle instance name.
- The host name, port number, and service name must be configured correctly in the tnsnames.ora file before running the Database Setup program. This file is located in the [ProPricer 9 Server program folder](#).
- System Username and Password: Username with SYSDBA privileges.
- System Temporary Tablespace Name
- Schema/Username and Password
- Data Tablespace Name
- Data Tablespace Path and Filename
- Index Tablespace Name
- Index Tablespace Path and Filename
- The ProPricer server needs to be connected to the pluggable database (PDB) that is connected to a container database (CDB).


## SQL Server Database Setup

After installing the application server, launch the Database Setup program. In Windows, go to Start > All Programs > ProPricer Server 9 > ProPricer Database Setup.

If the all-in-one installer is used, the Database Setup program runs automatically, and the database is created and upgraded automatically.

1. In the ProPricer Database Setup window, select Create a new Microsoft SQL Server Database, then click Next.
2. Enter the Microsoft SQL connection information, then click Test. If the connection is successful, click Next.
  - If you connect using Windows Authentication, read all the following Windows Authentication information for step 2. This information should not be skipped.
  - Windows Authentication is recommended for network environments.
  - In this example, localhost/ProPricerSQL is the database server, and Windows Authentication is used for the login information.





The screenshot shows the 'ProPricer Database Setup 9' window. The title bar is blue with the text 'ProPricer Database Setup 9' and standard window controls. The main content area has a white background with a blue header bar containing the text 'Microsoft SQL connection information' and a Microsoft SQL Server logo. Below the header, the text 'Enter the SQL Database Server and administrator login information.' is displayed. The 'Database Server:' field is a dropdown menu with 'localhost/ProPricerSQL' selected, and a 'Refresh' button is to its right. The 'Connect using:' section has two radio buttons: 'Windows Authentication' (selected) and 'SQL Server Authentication'. Below this, the 'Login:' field contains 'LAPTOP\Smith' and the 'Password:' field is empty. A 'Test' button is to the right of the password field. A checked checkbox labeled 'Trust Server Certificate' is below the password field. A green checkmark and the text 'The database connection test was successful.' are displayed. At the bottom, the text 'Executive Business Services, Inc.' is followed by three buttons: '< Back', 'Next >', and 'Cancel'.


3. When Windows Authentication is used, SQL Server Authentication is disabled, but the Application Host Name needs to be defined to allow access to the database.
4. For database creation and upgrade, the required roles are DBOwner, DBCreator, or the following individually assigned permissions: Create Database, Alter Database, Execute, Create Procedure, Create Table, Create Function, and Create Type.
5. For client connection, the required roles are DBOwner, DBCreator, or the following individually assigned permissions: Insert, Delete, Select, Update, and Execute.
  - If Windows Authentication is used, you must log on to the ProPricer Application Server 9 service with the correct account.
6. In Windows, open the Services console, right-click ProPricer Application Server 9, then click Properties.
7. Select Log On > This Account.
8. Enter the password then click OK or Apply.

9. Restart the ProPricer Application Server 9 service.
  - By default, Trust Server Certificate is selected, regardless of the authentication type. The option ensures a secure, encrypted connection with the database while using a self-signed SSL certificate. If your organization purchased a valid certificate and it is configured in SQL Server, clear the option.
10. Enter the Microsoft SQL database information, then click Next.
  - To create the ProPricer data structure within an existing SQL database, enter the name of that database.
  - Verify or change the currency. The default currency is US Dollar.
  - Selecting Grant database owner permissions for NT Authority/SYSTEM user gives the LocalSystem account permission to access the database.
  - Clearing Use default database file settings is only recommended for database administrators or advanced users who need to modify the minimum and maximum size of the database and log file.
11. Verify the settings, then click Create.

## Oracle Database Server Setup

When creating an Oracle database, the tnsnames.ora file must be configured with the correct host name, port number, and Oracle System ID (SID) before running the Database Setup program.

You can find an example tnsnames.ora file in the folder where ProPricer Application Server is installed. This file can be edited to include the required information, or a tnsnames.ora file can be copied to the folder from somewhere else, as long as the required information is correct.




After this is done, launch the Database Setup program.

1. In the ProPricer Database Setup window, select Create a new Oracle Schema, then click Next.
2. Enter the SID and login credentials, then click Test. If the connection is successful, click Next.
3. Enter and verify the schema and tablespace information, then click Next.
4. Verify the settings, then click Create.

## ProPricer Application Server Oracle Setup

When ProPricer Application Server is installed, Oracle Managed Driver is installed along with it. Neither the client nor application server for ProPricer require the Oracle client to be installed. However, before setting up the Oracle client, the `tnsnames.ora` file must be configured with the correct host name, port number, and Oracle system ID (SID). If this step was completed before running the Database Setup program, it does not need to be repeated.

You can find an example `tnsnames.ora` file in the folder where ProPricer Application Server is installed. This file can be edited to include the required information, or a `tnsnames.ora` file can be copied to the folder from somewhere else, as long as the required information is correct.



The screenshot shows a Windows File Explorer window with the following path: This PC > WINDOWS (C:) > Program Files > EBS > ProPricer Server 9. The window displays a list of files with columns for Name, Type, and Size. The `tnsnames.ora` file is highlighted in blue.

Name	Type	Size
System.ValueTuple.dll	DLL File	78 KB
<b>tnsnames.ora</b>	<b>ORA File</b>	<b>3 KB</b>
dbsetup.log	Text Document	1 KB
License.txt	Text Document	26 KB
ReadMe.txt	Text Document	1 KB

## Creating a Database Upgrade Script

To see what the upgrade process will change without affecting the current database, create a database upgrade script. Keep in mind that outdated clients will not be able to connect to the database after it is upgraded.

To generate a database upgrade script, the latest version of ProPricer Application Server must be installed, and ProPricer Database Setup must be run with command line parameters.

1. Go to [portal.propricer.com](http://portal.propricer.com), download the latest version of ProPricer Application Server, then install it.
2. In Windows, find the folder where ProPricer Application Server is installed. The default location is C:\Program Files\EBS\ProPricer Server.
3. Open the Command Prompt application.
4. Enter ProPricerDatabaseSetup /? to see all command line parameter options (optional).
5. Enter ProPricerDatabaseSetup.exe /t:upgrade /cn:CONNECTION\_NAME /tofile.
  - For example: ProPricerDatabaseSetup.exe /t:upgrade /cn:PP95\_104\_0\_SQL /tofile
6. If done correctly, a message will appear. Click OK.
7. The file you created will be named UpgradeScript\_CONNECTION\_NAME.sql.
  - For example: UpgradeScript\_PP95\_104\_0\_SQL.sql
8. Open the file in a text editor, such as Notepad, to see the changes that the upgrade process will make.

---

## Upgrading the Database

Installing new versions of ProPricer requires a database upgrade. To check if a database upgrade is required, see the release notes for the version of ProPricer you want to install.

To upgrade a database, the latest version of ProPricer Database Setup is required. Its default location is C:\Program Files\EBS\ProPricer Server 9.

1. Run the ProPricer Database Setup program, select Upgrade Existing Database, then click Next.
2. Select the Database Connection, click Test to make sure there is a connection to the database, then click Next.
3. Verify the settings, then click Upgrade.
  - The ProPricer client can be upgraded by running the client installer.

# Windows Service Account Configuration

If SQL Server is installed on a separate machine, a Windows service account may need to be configured to prevent a connection issue for your ProPricer users. Before configuring a Windows service account to work with the ProPricer Application Server 9 service the following must be completed:

- Set up a [SQL Server database](#)
- Create a Windows service account

When a SQL Server database uses Windows authentication and you test the database connection in ProPricer Server Manager, you might encounter a misleading successful connection message. This can happen because it tests the local user's account instead of the intended Windows service account. By default, the ProPricer Application Server 9 service runs under the local system account.

This connection issue can be resolved by configuring the Windows service account with the correct permissions before attempting to connect to ProPricer.

Set the following permissions to correctly configure the Windows service account:

1. ProPricer Application Server 9 service permissions:
  - Default schema: dbo
  - Database role membership: db\_owner
2. ProPricer Server folder permissions: Full Control
  - (Alternative) Add the service account to the local Administrators group

If the service account is not intended to be in the Administrators group, the ProPricer server certificate permissions must also be configured for the account. In the permissions, add the service account and grant it the Read permission.

# ProPricer Server Manager

Use ProPricer Server Manager to turn the service on and off, create connection files that connect ProPricer to its database server, manage ProPricer connections, view and remove active users, and maintain concurrent licenses. ProPricer Server Manager supports both SQL Server and Oracle databases.

## Using ProPricer Server Manager

Open ProPricer Server Manager by clicking Start > All Programs > ProPricer Server Manager 9.

- The Service page allows you to start or stop the ProPricer Application Server 9 service. Under Service Information, click Start or Stop.
- The Database Connections page is for testing the current connection or creating a new ProPricer connection file. Right-click the preferred connection, then select Generate Client Config File to create a .ppc file for that database. Once the .ppc file is created, it can be moved to any location.
- To manage database connections, the ProPricer Application Server 9 service must be running.
- Point ProPricer to the generated file by holding Shift on your keyboard when you start ProPricer for the first time.
- The Active Users page shows all connected users, how long they've been connected, and how long they've been idle. To disconnect a user from ProPricer, right-click the name, then select Disconnect Session.
- The Connections page is a log of the computers or profiles that have connected to the application server.
- The Concurrent Licenses page is for setting up and maintaining concurrent licenses. It is only used if the license type is Concurrent.
- The Options page lets you decide if you want ProPricer Server Manager to open automatically when Windows starts. You can also set the server port.
- The default port for ProPricer is 8092.
- After changing the port, you need to restart the service to make the change take effect.
- Closing ProPricer Server Manager will minimize it to the system tray.

# Ask Dela Setup

Ask Dela is a digital artificial intelligence assistant powered by Azure OpenAI models. It is designed to integrate seamlessly with existing infrastructure while maintaining strict data privacy and security standards.

How does Ask Dela operate in the background to deliver its capabilities?

- **Azure OpenAI integration:** Ask Dela leverages the power of Azure OpenAI services, utilizing cutting-edge GPT-4 models or higher to ensure high-quality responses and interactions.
- **User tenant deployment:** Ask Dela is deployed within the user's Azure tenant. This setup ensures all interactions and data remain within the user's own environment, enhancing security and compliance with organizational policies.
- **API key and configuration:** To activate Ask Dela, administrators must provide the appropriate API key and related information from their Azure OpenAI tenant. This ensures the assistant can authenticate and operate correctly within the specified tenant.
- **Data privacy and security:** One of the core principles of Ask Dela is maintaining the privacy and security of user data. We do not have access to any of the users' questions or data. All interactions with Ask Dela are processed within the user's own environment.
- **Data storage and management:** Users' questions and any related data are stored in the user's database. This data is under the user's control and can be managed as needed. Users can clear this data at any point, ensuring full control over their information.

To enable Ask Dela for ProPricer, you must create an Azure AI service and the required models, and then use ProPricer ServerConfig to point to the service.

The following sets of instructions in this section are optional. However, completing them allows ProPricer users to interact with and receive answers from Ask Dela.

## Creating an Azure AI service

1. Sign into the Azure Portal.
2. If you have access to multiple tenants, use the Directory + subscription filter in the top menu to switch to the tenant in which you want to register the application.
3. Search for and select Azure OpenAI services or Azure AI services.
4. Follow the instructions to create a new service. This will create the endpoint and keys required in ProPricer ServerConfig.



---

## Creating required models

1. Go to Azure AI Studio for the service you created.
2. Create a new deployment using the GPT-4 (completion) model.
3. Create a new deployment using text-embedding-ada-002 embedding model.

## Setting up ProPricer Server

1. Open the ProPricer ServerConfig tool.
2. In the AI Settings group, enter the endpoint and API key for your AI service.
3. In the Embedding group:
  - Enter the name of your embedding deployment.
  - In Model Id, enter text-embedding-ada-002.
  - In Request Delay, enter 1.
4. In the Completion group:
  - Enter the name of your completion deployment.
  - In Model Id, enter gpt-4.
5. Click Apply.
6. Restart ProPricer Application Server to apply the AI settings.


# ProPricer Client

Use the ProPricer client to access, manage, and report the data and proposals that are stored in the database. Regardless of the database type (SQL Server or Oracle), the client must be launched after the [database](#) has been set up and the [ProPricer connection file](#) (.ppc) has been created in ProPricer Server Manager.

- ProPricer license files are stored in the end user's roaming profile. If a system administrator is installing the ProPricer client, it should be activated with an end user's Windows credentials, not the administrator's credentials.

## Installing the ProPricer Client

1. Double-click the ProPricer client installation file.
2. Select the installation language, then click Next.
3. Optionally, enter your registration key, then click Next. If you copied the key to your clipboard, click Paste instead of pressing Ctrl+V.
4. Enter your registration key, then click Next. If you copied the key to your clipboard, click Paste instead of pressing Ctrl+V.
5. Accept the default location for the client files, or click Browse to select a different folder, then click Next.
6. If needed, change the program folder's name, then click Next.
7. Select or clear any of the additional options, then click Next.
  - Create a desktop icon for ProPricer after installation.
  - When ProPricer is opened, notify the user that a .ppc file must be selected to connect to the database server.
8. Verify the settings, then click Install.
9. Click Finish.
10. The first time ProPricer starts, the client will need to be pointed to the database using the .ppc file created in ProPricer Server Manager. To do this, hold Shift while starting ProPricer, select the file, then click Open.



11. Enter your registration key, then click Register. If you already provided the key during step 4, it will be entered here automatically.
12. For the ProPricer login type, the default login name and password are both sysadmin. If you encounter an error that prevents you from logging in, contact ProPricer Technical Support for troubleshooting.

---

## Upgrading the ProPricer Client

If an upgrade is available, the application server and the database must be upgraded first before the client can be upgraded. If the client is upgraded but the database and application server are not, or vice versa, the client will not be able to connect to the server.

- The ProPricer client and application server installed must be the same version number.

To upgrade the ProPricer client, download the installation file for the latest version of ProPricer at [downloads.propricer.com](https://downloads.propricer.com) on the My Products tab. Double-click the file to [run the installation](#).

# All-In-One Installation

The client, server, and MSSQL Express (all-in-one) installation file is only recommended for standalone installations. Use it if:

- The ProPricer client, application server, and database are going to be on the same system.
- The system is not intended to be connected to a network ProPricer setup.

Because an [SSL certificate is required](#) for secure client-server communication, the all-in-one installation creates a self-signed certificate. It also completes the server configuration automatically so the certificate can be used.


## Troubleshooting a Connection Error

You might receive the following error message:


Cannot open database “NAME BASE NAME” requested by the login. The login failed. Login failed for user “USER NAME HERE”.

If you encounter this error, the ProPricer Application Server service needs the correct account to properly authenticate with the database.


1. Verify the [Windows service account configuration](#). The service account must be configured with the following permissions for the ProPricer Application Server 9 service.
  - Default schema: dbo
  - Database role membership: db\_owner
2. Press Windows Key+R. When prompted, type Services.msc, then click OK to open the Services console.




3. In the console, right-click ProPricer Application Server 9, then click Properties.



4. In the properties, click Log On and enter the service account credentials that will be used to access the ProPricer database.



5. A prompt to restart the application server service will appear. Click OK. You can restart the service with the option provided in the Services console (next to the list of services). Alternatively, you can open ProPricer Server Manager and restart the service there.



# Remote Desktop Services or Citrix Server

ProPricer uses RAM heavily. For each user session running on a Remote Desktop Session Host server or Citrix server, at least 2 GB of RAM should be dedicated to the ProPricer client.

ProPricer licensing information is stored in a user's roaming profile. When using a Remote Desktop Session Host server or Citrix server, the user's roaming profile must be preserved to maintain the licensing information.

- Concurrent licenses are recommended in this type of environment.

## Prerequisites

- .NET 8 (not included with installation)

## Downloads

The ProPricer client and server installation files can be downloaded from the ProPricer Support Portal by a user with a license role. The portal is located at [portal.propricer.com](https://portal.propricer.com), and the installation files can be found in the Products & Licenses tab. Or you can go directly [to downloads.propricer.com](https://downloads.propricer.com).

## Installing the ProPricer Client on a Remote Desktop Services or Citrix Server

Repeat the first nine steps from the [Installing the ProPricer Client](#), then begin with step one of the following procedure.

1. Open Citrix Studio. After adding a VDA image to Machine Catalogs and Delivery Groups, click Applications > Add Applications.
2. Click Next.
3. Select one or more delivery groups, then click Next.
4. Click Add > From start menu. This will search for available applications.
5. After a search of the available applications, select ProPricer 9, then click OK.
6. Click Next.



# Command Line Arguments for ProPricer Tools

## Database Setup: ProPricerDatabaseSetup.exe

```
ProPricerDatabaseSetup /t:showversion [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:showversion /cn:[CONNECTION_NAME] [<optional-arguments>]
```

### Usage for MSSQL

```
ProPricerDatabaseSetup /t:createmssql /u:[USERNAME] /p:[PASSWORD] /sn:[SERVER_NAME] /db:[DATABASE_NAME] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:createmssql /wa /sn:[SERVER_NAME] /db:[DATABASE_NAME] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:createmssql /db:[DATABASE_NAME] /tofile [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:upgrade /cn:[CONNECTION_NAME] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:drop /cn:[CONNECTION_NAME] [<optional-arguments>]
```

### Usage for Oracle

```
ProPricerDatabaseSetup /t:createoracle /db:[SCHEMANAME] /p:[PASSWORD] /dba:[DBA_USER/DBA_PASSWORD] /sn:[INSTANCE_NAME] /tsp_data:[DATA_TABLESPACE_PATH] /tsn_data:[DATA_TABLESPACE_NAME] /tsp_index:[INDEX_TABLESPACE_PATH] /tsn_index:[INDEX_TABLESPACE_NAME] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:createoracle /db:[SCHEMANAME] /p:[PASSWORD] /dba:[DBA_USER/DBA_PASSWORD] /sn:[INSTANCE_NAME] /tsp_data:[DATA_TABLESPACE_PATH] /tsp_index:[INDEX_TABLESPACE_PATH] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:createoracle /db:[SCHEMANAME] /p:[PASSWORD] /tsp_data:[DATA_TABLESPACE_PATH] /tsp_index:[INDEX_TABLESPACE_PATH] /tofile [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:upgrade /cn:[CONNECTION_NAME] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:upgrade /cn:[CONNECTION_NAME] /tsn_data:[DATA_TABLESPACE_NAME] /tsn_index:[INDEX_TABLESPACE_NAME] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:drop /cn:[CONNECTION_NAME] /dba:[DBA_USER/DBA_PASSWORD] [<optional-arguments>]
```

```
ProPricerDatabaseSetup /t:drop /cn:[CONNECTION_NAME] /dba: [DBA_USER/DBA_PASSWORD] /tsn_data:[DATA_TABLESPACE_NAME] /tsn_index:[INDEX_TABLESPACE_NAME]
[<optional-arguments>]
```

### Options

Command	
/h or /?	Show this command line argument help information.
/t	The process type to execute. Options are: createmssql createoracle upgrade drop showversion
/u	The database user that will be used to connect. If Windows Authentication is used, this will be ignored.
/p	The database password that will be used to connect. If Windows Authentication is used, this will be ignored.
/wa	[Boolean] Uses Windows Authentication to connect to the database.
/sn	The database server name (MSSQL) or service name (Oracle) that will be used to connect.
/db	The database name (MSSQL) or schema name (Oracle).
/gsys	Optional. Grant MSSQL database owner permissions for NT AUTHORITY\SYSTEM user.
/cn	The connection name used.
/tsn_data	The data tablespace name used to create or upgrade an Oracle database. If this value is omitted, the name will be like: {SCHEMANAME}_DATA

Command	
/tsn_index	Optional. The index tablespace name used to create or upgrade an Oracle database. If this value is omitted, the name will be like:  {SCHEMANAME}_INDEX
/tsn_temp	Optional. The temporary tablespace name used to create an Oracle database. If this value is omitted, the name will be like:  TEMP
/tsp_data	The path where the data tablespace will be stored in the Oracle server.
/tsp_index	The path where the index tablespace will be stored in the Oracle server.
/dba	The Oracle system DBA user information. Required when creating a schema. Format:  USER/PASSWORD
/c	Optional. The default currency for the system. If this value is omitted, USD will be used by default. Options are:  AUD CAD CNY EUR GBP JPY MXN USD
/tofile	Optional. This will output the script instead of executing it.
/v	Optional. Run the process in Verbose mode.
/q	Optional. Run the process in Quiet mode. On-screen messages will not appear.
/uv	Optional. Run the process in Upgrade View.

## ProPricer ServerConfig: ProPricerServerConfig.exe

### Usage

```
ProPricerServerConfigTool.exe /host:[HOST] /p:[PORT] /s[SUBJECT] /sn[STORENAME]
```

### Options

- /h or /? Show this command line argument help information.
- /host The host name/IP of the ProPricer application server.
- /p The IP port on which the ProPricer application server listens for connections.
- /s The subject name of the SSL certificate that will be used. This name must match the host name.
- /sn The name of the store that will be searched for the SSL certificate.

## Server Manager: ProPricerServerManager.exe

### Usage

```
ProPricerServerManager.exe [/serviceHost:<host>] [/servicePort:<port>] [/quiet]
```

### Options

Command	
/h or /?	Show this command line argument help information.
/serviceHost:<host>	The host name/IP of the ProPricer application server.
/servicePort:<port>	The IP port on which the ProPricer application server listens for connections.
/q	Optional. Run the process in Quiet mode.

# Silent Installation, Upgrade, or Removal

Use command prompts or Microsoft System Center Configuration Manager (SCCM) to run a silent installation, silent upgrade, or silent removal of ProPricer. A silent installation can be helpful when ProPricer is needed on multiple machines.

Before any action can be taken, the correct .zip file needs to be downloaded from the ProPricer Support Portal and extracted to a folder. For example, the file for Contractor Edition is called 9\_5\_104\_0\_pp\_ce\_client\_sccm.zip, and the file for subscription licenses is 9\_5\_104\_0\_pps\_ce\_client\_sccm.zip. Windows File Explorer can be used to extract these files.

## Running a Silent Installation

Find the extracted files that were downloaded from the ProPricer Support Portal and make sure the file SetupInstall.iss is included, then run this command as an administrator:

```
9_5_104_0_pp_ce_sccm.exe /s /f1"C:\Users\QA\Desktop\9_5_104_0_pp_ce_sccm\SetupInstall.iss"
```

Notice that the only spaces in the string are before and after /s. The s means that the command is being run in "silent" mode.

If you would like to edit the parameters that the file installs ProPricer with, open the file in Notepad and make your desired changes. For example, if you would like the installation to create a default .ppc connection file, change the string CreateDefaultPPC=0 to CreateDefaultPPC=1.

If you would like to include your own .ppc connection file in the installation, place a copy of the file in the extracted folder location prior to running the silent installation file.

To generate a log file for the installation, add the parameter /f2. For example, /f2"C:\result.log"

## Recording the Installation Process

To record the installation process, rather than edit the SetupInstall.iss file to set your parameters, go to the folder that contains the extracted files, then run this command as an administrator:

```
9_5_104_0_pp_ce_sccm.exe /r /f1"C:\Users\QA\Desktop\9_5_104_0_pp_ce_sccm\SetupInstall.iss"
```

Notice that the only spaces in the string are before and after /r. The r means that the command is being run in "record" mode.

After the .iss file has been set up to record, double-click the 9\_5\_104\_0\_pp\_ce\_client\_sccm.exe file and install ProPricer with your desired parameters. Make sure this is a clean installation to ensure that your parameters are recorded correctly.

---

## Running a Silent Upgrade

Run a silent upgrade of ProPricer with the SetupUpdate.iss file by running this command as an administrator:

```
9_5_104_0_pp_ce_client_sccm.exe /s /f1"C:\Users\QA\Desktop\9_5_104_0_pp_ce_client_sccm\SetupUpgrade.iss"
```

- Note: For all the possible settings and parameters, go to [docs.reverera.com/installshield19helplib/helplibrary/IHelpSetup\\_EXECmdLine.htm](https://docs.reverera.com/installshield19helplib/helplibrary/IHelpSetup_EXECmdLine.htm)

## Running a Silent Removal

Run a silent removal of an installation with the SetupRemove.iss file by running this command as an administrator:

```
9_5_104_0_pp_ce_sccm.exe /s /f1"C:\Users\QA\Desktop\9_5_104_0_pp_ce_sccm\SetupRemove.iss"
```

# Contact Us

For assistance installing ProPricer, please visit the Deltek Support Center at [deltek.custhelp.com](https://deltek.custhelp.com).